

i-Code CNES Installation Manual


Ref: DNO/DA/AQ - 2017.0002479

Date: 24/05/2018

Page: 1/6

Installation Manual i-Code CNES

DNO/DA /AQ - 2017.0002479 Version 3.0.1



i-Code CNES Installation Manual

Réf: DNO/DA/AQ - 2017.0002479

Date : 24/05/2018

Page: 2/6

Table of contents

1.	INTRODUCTION	. 3
2.	QUICK INSTALL	. 3
	2.1.DOWNLOAD I-CODE CNES	
	2.2.I-CODE CNES COMMAND LINE	.3
	2.3.I-CODE CNES IDE	.3
	2.4. ECLIPSE PLUG-IN I-CODE CNES	.4

i-Code CNES Installation Manual

Réf: DNO/DA/AQ - 2017.0002479

Date : 24/05/2018

Page: 3/6

1. INTRODUCTION

This document explains how to install i-Code CNES.

This tool provides 3 products:

- Standalone version,
- Command line version
- · Eclipse plugins version, tested with Oxygen.

2. INSTALLATION GUIDELINES

2.1. DOWNLOAD I-CODE CNES

i-Code CNES executables are available on the release page from github i-CodeCNES repository page : https://github.com/dupuisa/i-CodeCNES/releases

For each release, the following products are available:

- icode.exe: command line version.
- I-CodeCNES-IDE-Release-3.0.1.zip: standalone version.
- i-CodeCNES-Release-3.0.1: eclipse plugin version, update site.

2.2. I-CODE CNES COMMAND LINE

Command line version does not need to be installed. You can use it as is.

2.3. I-CODE CNES IDE

Unzip i-CodeCNES-IDE-Release-3.0.1.zip. You can directly use your standalone version without other installation.

i-Code CNES Installation Manual

Réf: DNO/DA/AQ - 2017.0002479

Date: 24/05/2018

Page: 4/6

2.4. ECLIPSE PLUG-IN I-CODE CNES

i-Code CNES as eclipse plugins has to be installed following the next steps:

- 1. Launch eclipse.
- 2. Select menu Help > Install New Software...




Figure 1: eclipse plugin installation

3. Click on « Add... »




Figure 2: installation folder

- 4. Click on « Archive... » and select i-CodeCNES-Release-x.x.x.zip.
- 5. Give a name to this install folder, for example i-CodeCNES-Release-x.x.x.zip
- 6. Click on « OK »

i-Code CNES Installation Manual

Réf: DNO/DA/AQ - 2017.0002479

Date: 24/05/2018 Page: 5/6

Following plugins are available.




Figure 3: Available plugins

7. Select all and click on « Next ».




Figure 5: Installation details

- 8. Click on « Next ».
- 9. Accept the license.
- 10. Click on « Finish ».




Figure 6: plugin installation

i-Code CNES Installation Manual

Réf: DNO/DA/AQ - 2017.0002479

Date: 24/05/2018 Page: 6/6

11. When the following window appears, click on « Yes ». eclipse restart.




Figure 7: eclipse restart window

12. When eclipse restart is done, a new menu « i-Code CNES » appears, the installation is done.




Figure 8: i-Code CNES menu

**** END OF DOCUMENT ****